



LAWRENCE  
LIVERMORE  
NATIONAL  
LABORATORY

# Visualization with VisIt Class Exercises

*B. J. Whitlock*

**February 2005**

This document was prepared as an account of work sponsored by an agency of the United States Government. Neither the United States Government nor the University of California nor any of their employees, makes any warranty, express or implied, or assumes any legal liability or responsibility for the accuracy, completeness, or usefulness of any information, apparatus, product, or process disclosed, or represents that its use would not infringe privately owned rights. Reference herein to any specific commercial product, process, or service by trade name, trademark, manufacturer, or otherwise, does not necessarily constitute or imply its endorsement, recommendation, or favoring by the United States Government or the University of California. The views and opinions of authors expressed herein do not necessarily state or reflect those of the United States Government or the University of California, and shall not be used for advertising or product endorsement purposes.

This work was performed under the auspices of the U.S. Department of Energy by University of California, Lawrence Livermore National Laboratory under Contract W-7405-Eng-48.

## Introduction

This document contains the exercises for the *Visualization with VisIt* class. The exercises are broken down into sets that can be completed as the class progresses and you become more familiar with using VisIt. The VisIt class allows time for the first few exercises in each exercise group, making the remaining exercises optional.

## Conventions

This document will usually give the exact steps needed to complete the exercises but exercises will get more difficult and sometimes you will only be given the name of a database and an image of a plot, leaving you to figure out how to recreate the image using your acquired knowledge of VisIt's features. Some exercises within an exercise group require the successful completion of the previous exercise.

Text formatting conventions

- Names of controls or windows in VisIt's user interface will appear in **bold** print but words like: window, button, list, and menu will not usually be printed in bold print.
- When you are asked to type text, the text will be *italicized*.
- Filenames will be *italicized*.

## Organization

The organization of this exercise guide roughly follows the topics discussed in the Visualization with VisIt class, though sometimes new concepts may be introduced before they have been discussed in the class for the sake of providing more interesting exercises.

## Tips before you begin

- It might be helpful if you close the compute engine every once in a while after making it do a lot of computations to free up memory and resources. Closing the compute engine is especially important if you notice that your Windows desktop computer becomes sluggish.

## Exercise group 1: Working with files

The exercises in this section will give you experience for browsing the file system and selecting files using VisIt's **File selection window**.

### Exercise 1a) Filtering out unwanted files

This exercise teaches you how to open the **File selection** window and use it to select files that you can plot in VisIt.

1. Open the **File selection window** by clicking on **Select files ...** in the **Main window's Controls** menu.
2. Type *C:\Program Files\LLNL\VisIt 1.4.1\data* into the **Path** text field and press the Enter key. Many data files should appear in the **Files** pane of the **File selection window**.
3. Click the window's **Remove all** button to clear out the files in the selected files list.
4. Type *multi\*.silo* into the **Filter** text field and press the Enter key. This will filter out the files that do not begin with "multi" from the list of available files.
5. Click the **Select all** button to select all of the files in the available files list so they appear in the selected files list.
6. Click the **OK** button to accept the new list of selected files and dismiss the window. The selected files list in the **Main window's File panel** should now only contain a handful of files that begin with "multi".

### Exercise 1b) Opening a file

Now that the selected files list contains some selected files that begin with "multi", which for the test databases indicates that there are multiple domains in each file, you are ready to begin opening files.

1. Click on *multi\_rect3d.silo* in the **Selected files** list to highlight the file.
2. Click the **Open** button to open the file.
3. Notice that the **Plot and Operator** menu in the **Plot list area** becomes active since there is now an open database.
4. Click on the **Plots** menu option in the **Plot and Operator** menu to see that most plot types have variables that they can plot. When a plot type has variables that it can use to create a new plot, it is enabled in the menu.
5. Open the **File information** window by clicking on **File information ...** in the **Main window's File** menu. The **File information** window displays information about the currently open file such as the names of its variables, how many time steps it contains, etc.
6. Click the **File information** window's **Dismiss** button.

### Exercise 1c) Making a plot

Now that you know how to open a file, and you have opened a file, you can make a plot with that file. We will not cover making a plot in great detail at this point since that will be done later but you will at least learn the basics of creating a plot here.

1. Click the **Plots** menu option in the **Plot and Operator** menu.
2. Move the mouse down the list to the **Pseudocolor** option. This should bring up a small pull-right menu (a **variable** menu) containing the variables from the open file that a Pseudocolor plot can use.

3. Select the **d** option from the Pseudocolor plot's **variable** menu to create a Pseudocolor plot of the variable *d*. Notice that a Pseudocolor plot entry appears in the **plot list** in the center of the **Main** window.
4. Click the **Draw** button above the **Plot list** in the **Main** window to make VisIt draw the plot and put it in the visualization window.
5. Click the **Delete** button to delete the plot from the **plot list**.

### Exercise 1d) Opening .visit files

Some database file formats are capable of storing multiple time steps in a single file but most formats only support storing a single time step in a file. VisIt's animation controls are only enabled for databases with multiple time steps. If you have a set of files where each file is a time step in a larger time-varying database, you need to tell VisIt how to recognize all of your files as being related in a larger time-varying database. VisIt supports a .visit file, which is a text file with the .visit extension that contains all of the names for each time state in your time-varying database.

1. Click on the Windows **Start** menu button in the lower left corner of the screen.
2. Click on the **Run ...** option in the Windows **Start** menu.
3. Type: `wordpad "C:\Program Files\LLNL\VisIt 1.4.1\data\wave.visit"` to open *wave.visit* in wordpad so you can examine the contents of the *wave.visit* text file.
4. Close wordpad.
5. Open VisIt's **File selection** window by clicking on the **Select files...** option in the **Main** window's **Files** menu.
6. Type: `*.visit` into the **Filter** text field so only files that end in .visit will be shown in the **Files** list.
7. Click the **Remove all** button to clear out the **selected files** list.
8. Click the **Select all** button to add *wave.visit* to the **selected files** list.
9. Click the **OK** button to use the new **selected files** list and dismiss the **File selection** window.
10. Click on *wave.visit* in VisIt's **selected files** list and click the **Open** button. Opening a file that has multiple time steps places a green database icon next to it in the list and expands the database to show all of the cycles that it contains.

### Exercise 1e) Automatic file grouping

Using .visit files is required in some cases, but often you can try and have VisIt guess how sets of files are related instead of using a .visit file. VisIt provides a feature called *Automatic file grouping*, which causes the database server to scan the list of filenames that it reads from the file system and return them to other VisIt components as a single database entity that we call a virtual database.

A virtual database is a group of related files that have been combined into a database that has no corresponding file on disk. VisIt can sometimes guess file relations incorrectly if the filenames for unrelated files match closely enough to the files that are part of a virtual

database. Sometimes, you will need to use the filter in the **File selection** window to make sure a virtual database contains only the files that you wanted to be in the virtual database.

Automatic file grouping is enabled by default but it can be turned off so related files are no longer grouped into virtual databases. If automatic file grouping is off and if you have no .visit file to group files, the animation controls in the **File panel** will not work when you open one of the individual time step files because they only have a single time step.

1. Open the **File selection** window by clicking the **Select files...** option in the **Main** window's **File** menu.
2. Type: *w\*.silo* into the **Filter** text field and press the Enter key to cause the new filter to take effect and populate the **Files** list with only files that begin with *w* and end in *.silo*. The only entry in the **Files** list should be a virtual database called: *wave\*.silo database* and it will have a few dozen file names under it but they are part of the virtual database.
3. Select the *Off* option from the **File grouping** combo box to turn off automatic file grouping. Note that the *wave\*.silo database* disappears and is replaced by the individual filenames.
4. We usually always want automatic file grouping to be enabled so turn it back on by selecting *Smart* or *On* from the **File grouping** combo box.
5. Click the **Remove all** button to clear out the **selected files** list.
6. Click the **Select all** button to add *wave\*.silo database* to the **selected files** list.
7. Click the **Ok** button to use the new selected files list and dismiss the **File selection** window.

### Exercise 1f) Opening at late time in a virtual database

Files with multiple time steps normally cannot be opened at time state other than the first time state. Virtual databases, on the other hand, can be opened at later time states because they are initially expanded to show all of the files for the database in the **File panel**.

Sometimes it is convenient to open a virtual database at a later time state because new variables appear later in the time series. VisIt normally uses the metadata, which is the information that the **File information** window displays, from the first time state in the time-varying database that is opened. This means if you open the virtual database at the first time state, the list variables will only be the variables that are known in the file that corresponds to the first time state. If you know that new variables appear later in the time series, then you can open the virtual database at that later time state so the variables that appeared later will be available for plotting.

1. Click on *wave0170.silo* in the *wave\*.silo database* virtual database in the **selected files** list to highlight that later time state.
2. Click the **Open** button to open the *wave\*.silo database* virtual database at the late time state: *wave0170.silo*, which has a variable that earlier time states do not have. Note that the **animation slider's** active time state is set to a point about 25% through the length of the **animation slider**.

3. Open the **File information** window by clicking **File information ...** in the **Main** window's **File** menu. The **File information** window always shows the file information for the currently open database, which in this case should be: *wave\*.silo database*. Note that it is a virtual database and has several time states. Also note that since the database was opened on a later time state, there is a scalar variable called: *transient* that does not appear in earlier time states.
4. Click the **Dismiss** button in the **File information** window to dismiss the window for now.
5. Under the **Open** and **Replace** buttons in the **Main** window's **File panel**, there is an **animation slider**. The **animation slider** shows where the active time state is relative to the entire number of database time states and allows you to set the active time state for the open database. Since we opened *wave\*.silo database* on cycle 17, the animation slider should be about 25% of the way through the database. Click on the **animation slider** and drag it back to the first time state.

### Exercise 1g) Reopening a database

VisIt allows you to reopen a database. Here are some common reasons for wanting to reopen a database:

- The file changed on disk
- You have a running simulation and more time states were added to the database
- You have switched to a later time state that you know has a new variable and you want that variable to appear in the variable lists.

When you open a database using VisIt, the currently open database is set to the database that you opened and the **Open** button turns into a **ReOpen** button. If you highlight another database that you have never opened, the **ReOpen** button turns back into the **Open** button. If you highlight another database that you have previously opened, the **ReOpen** button turns into the **Activate** button. When you click the **ReOpen** button, VisIt discards any cached information about the database and rereads that information from the database server so variable lists, etc can be updated using the new database information. Also, any plots that used the database are regenerated by the compute engine after it reopens the database.

1. Open the **File selection** window by clicking on **Select file ...** from the **Main** window's **File** menu.
2. Type: *\*.visit* into the Filter text field and press the Enter key to apply the new filter to the list of files. This should cause a new set of files to show up in the **Files** list. All of the new files should have the *.visit* extension.
3. Click the **Remove all** button to remove old files from the **selected files** list.
4. Click on *wave.visit* in the **Files** list and then click the **Select** button, which should now be enabled. Clicking the **Select** button adds the highlighted items in the **Files** list to the **selected files** list.
5. Click the **OK** button to accept the new **Selected files** list and dismiss the **File selection** window.

6. Click on `wave.visit` in the selected files list in the **File panel** to highlight that database.
7. Click the **Open/Activate** button to open `wave.visit`. This should cause it to have a green database icon added to it and all of its time states should be expanded under it. In addition, the database will be open at the first time state.
8. Click on the **Plots** option in the **Plots and Operators** menu to show the **Plots** menu. Add a Pseudocolor plot of `pressure` by moving the mouse down over the **Pseudocolor** option in the **Plots** menu and clicking on `pressure` in the **variable** menu.
9. Click the **Draw** button to make VisIt draw the new plot.
10. Use the **animation slider** under the **ReOpen** and **Replace** buttons in the **Main** window to set the active time state to be `0170`. Note that as you move the **animation slider**, the **Time** text field next to it will display the cycles for the database. Stop moving the **animation slider** once the **Time** text field contains `0170`.
11. Recall from the previous exercise that the `wave*.silo database` database had an extra variable called `transient` that appeared at cycle `0170`. The `wave.visit` database is equivalent to `wave*.silo database`, except that the latter is a virtual database. Look at the variable list now that the active time state is `0170`. Note that the variable `transient` is not available. This is because we opened the `wave.visit` database at the first time state.
12. Click the **ReOpen** button to make VisIt reopen the `wave.visit` database at the current time state.
13. Click on the **Delete** button next to the **Draw** button above the plot list to delete the plot of `pressure`.
14. Click on the **Plots** option in the **Plots and Operators** menu to show the **Plots** menu. Add a Pseudocolor plot of `transient` by moving the mouse down over the **Pseudocolor** option in the **Plots** menu and clicking on `transient` in the **variable** menu.
15. Click the **Draw** button to make VisIt draw the new plot.
16. Click the **Delete** button to make VisIt delete the plot.

## Exercise 1h) Replacing a file

VisIt provides support for database replacement, which replaces the databases in the plot list with a new database. If the new database has the same variables as the old database, the plot is regenerated using the new database. However, if you are replacing with the same database but with a different time state, then VisIt will just set the active time state instead of replacing the databases for the plots in the plot list.

1. Click on the **Plots** option in the **Plots and Operators** menu to show the **Plots** menu. Add a Pseudocolor plot of `u` by moving the mouse down over the **Pseudocolor** option in the **Plots** menu and clicking on `u` in the **variable** menu.
2. Click the **Draw** button to make VisIt draw the new plot.



3. Click on the first time state of *wave.visit* in the **selected files** list and then click the **Replace** button to make VisIt switch the time state for *wave.visit* back to the first time state.
4. Open the **File selection** window by clicking on the **Select files ...** option in the **Main** window's **File** menu.
5. Type: *\*.silo \*.visit* into the **Filter** text field and press the Enter key to make VisIt use the new file filter.
6. Click the **Select all** button to add all of the files the **Files** list to the selected files list.
7. Click the **OK** button to accept the new **Selected files** list and to dismiss the window.
8. Click on the *globe.silo* file in the **selected files** list in the **File panel** so it is highlighted.
9. Click the **Replace** button to make VisIt replace the current plot from *wave.visit* with a plot from *globe.silo*. This will work because both databases have a variable called *u*. If the database we're using to replace did not have a variable called *u*, VisIt would issue an error message and not regenerate the plot. Note that the **Animation slider** is no longer enabled since the new database has only one time state.
10. Click the **Delete** button to make VisIt delete the plot.

## Exercise group 2: Remote visualization

Most of the time, data is generated in parallel on large supercomputers either on site or at other locales. Few users run simulations on their desktop computers so in order to visualize data that was generated on remote computers, the data either has to be moved locally to the desktop, if the data is small enough, or moved to a powerful visualization server where it can be processed. There are two problems with this because the data either has to be moved or performance suffers from having to display the visualization code back to the desktop computer through secure shell. To remove both of these obstacles to visualization, VisIt allows you to do distributed computing, where you can run VisIt locally on your desktop computer but have all of the data processing done in parallel on the same machine that generated the data.

In order to run in distributed mode, VisIt needs to know how to run on the remote computer. You can furnish information about where to look for the VisIt executable or how many processors to use when running in parallel using host profiles. A host profile contains all of the information that VisIt needs to run its compute engine and database server on the remote computer.

*Note -- Offsite class participants can skip the portions of this exercise group that deal with getting connected to a remote computer. Any further mention of files on the "remote" computer can be disregarded and files located in C:\Program Files\LLNL\VisIt 1.4.1\data or /usr/gapps/visit/data can be used for the remainder of the class exercises.*

OTP tokens for workshop accounts on an LC computer will be provided during the class. Any instructions that require you to type a name of an LC computer will use: *REMOTEHOST* for the name of the computer since the computer that is used from class to class can vary. When you see *REMOTEHOST*, substitute the name of the computer provided by the class instructor.

## Exercise 2a) Testing secure shell and OTP token

This exercise tests out the OTP token and the ability of your classroom computer to run secure shell to connect to a remote computer and will familiarize you with running F-secure shell.

1. Click on the Windows **Start** menu on the bottom left of the screen.
2. Click on the **Programs** menu.
3. Click on the **F-secure** menu option and select **F-Secure client** from the list of F-Secure options. This will launch the F-Secure application so you can test out your computer's ability to connect to a remote computer.
4. Click on the application's **Quick Connect** button to start connecting to a remote computer. This will activate the **Connect to Remote Host** dialog.
5. Type *REMOTEHOST* into the **Host name or IP address** text field.
6. Look at the account name printed on your OTP token. It will be of the form: *class##*. Type that account name into the **User Name** text field. **Do not use the student account name that you used to log into the desktop computer because that account name is not valid on the remote computer!**
7. Click the **Connect** button.
8. F-Secure should prompt you for a password at this point with a new password dialog. If F-Secure instead tries to log you into *REMOTEHOST* without asking for a password, the log-in will fail. If this happens to you, type 922 into the **Port** text field and click the **Connect** button again.
9. Once F-secure shows the password dialog, type the workshop account's PIN, which will be provided by the class instructor, plus the six digit number that appears in the OTP token. Make sure that when you start using a number from the OTP token that you type it quickly since the number changes every 5-10 seconds. If F-Secure rejects your password then try a few more times. If it still does not work, ask the instructor for a new OTP token.
10. When F-secure accepts your password, it should log you into *REMOTEHOST* and give you a UNIX command prompt.
11. Type *spj* and press the Enter key at the command prompt if you want to see the status of all of the compute jobs on *REMOTEHOST*.
12. Type *ju* and press the Enter key at the command prompt if you want to see a short list of available compute nodes.
13. If for some reason, you ever want to remove a job from the queue, type *prm* followed by the job id (JID) reported by *spj*.
14. Leave F-Secure open but minimize it so it is not in the way. We keep the application open so that later you can check on the status of your parallel jobs or remove them from the batch queue, if necessary.

### Exercise 2b) Setting up a host profile (optional)

In this exercise, you will set up a host profile to access files on *REMOTEHOST* and ultimately to do visualization by having VisIt's parallel compute engine run there in the batch queue. Setting up a host profile might seem a little involved but host profiles for the most popular computers on LC's open and closed networks come preloaded with VisIt so you may never have to create your own host profile again. The class instructor will let you know if this exercise is required and if it is required then the instructions will be provided in class.

### Exercise 2c) Accessing files on *REMOTEHOST*

Using the host profile created in the previous exercise, it is time to try and access files on *REMOTEHOST*. Note that you will need to enter your token password when VisIt prompts you in order to get VisIt's database server to run on *REMOTEHOST*.

Be *careful* when trying to access files on a remote computer using the Windows version of VisIt because, unlike its UNIX counterparts, the Windows version is not as good at detecting failures to launch VisIt components on the remote computer. If you make a mistake, it is possible that you will have to restart VisIt! This is only a shortcoming in the Windows version of VisIt. The UNIX versions, including the Linux version, do not have any problems detecting failures to launch remote VisIt components. Not only that, the UNIX versions of VisIt can be even set up to operate without a password using password-less ssh (secure shell).

1. Open VisIt's **File selection** window by clicking on **Select files...** in the **Main window's File** menu.
2. Click on the **Host** combo box to view its list of available hosts.
3. Select *REMOTEHOST* from the list of available hosts. This prompts VisIt to launch a database server on *REMOTEHOST*.
4. You may see a flashing item in the **Windows task bar**, which is located all along the bottom of the screen. Click on it to bring up the **Connection progress** dialog. Note that on Windows, other applications are not permitted to raise their windows over the active application so you have to make the **Connection progress** dialog active yourself by clicking on it.
5. Not long after initiating a connection, VisIt will prompt you for your password with the **Password** window. Enter your pin number and the token number and press the Enter key. If your password is not accepted, the **Password** window will pop up again. If your password is accepted, the **File selection** window will, after a short pause, display files from *REMOTEHOST*.
6. Type `/usr/gapps/visit/data` into the **Path** text field and press the Enter key so VisIt will display the data files in that remote data directory.
7. Select all of the files in the remote data directory by clicking the **Select All** button.
8. Click the **OK** button to accept the new selected files list.

## Exercise 2d) Posting the compute engine window

The **Compute engine** window displays the progress for a compute engine while the engine is generating plots. Progress is useful so you can gauge how much time an operation will take. In addition to showing progress, the **Compute engine** window also has a button to interrupt a compute engine so you can interrupt a compute engine if it takes too long. The **Compute engine** window also has a **Close engine** button so you can close a compute engine if you no longer need it.

1. Click the **Compute engines ...** option in the **Main** window's **File** menu to activate the **Compute engines** window.
2. Click the **Compute engines** window's **Post** button to post it to the **Notepad area**.

## Exercise 2e) Making plots from remote files and local files

Making plots from remote files is no different from making plots with local files once you have the files in your selected files list. The same vis window can even contain plots from databases that are located on different computers.

1. If you have files from your local Windows computer, the selected files list will now contain a tree of files where the root of the tree is *Hosts*. Scroll down to near the bottom of the selected files list and expand the *REMOTEHOST* branch by clicking on the little plus symbol to the left of the name. Open *multi\_ucd3d.silo* on *REMOTEHOST* by clicking on that filename to highlight it and then click the **Open** button.
2. Since there is a host profile for *REMOTEHOST* that is parallel, VisIt will open the **Profile chooser** window, which allows you to choose how many processors to use before launching a compute engine on *REMOTEHOST*. Choose the *parallel pbatch* profile and do not change the number of processors, etc. since we already set that up in a previous exercise.
3. After the **Profile chooser** window is dismissed, VisIt will show the **Connection progress** dialog again with a message indicating that a parallel compute engine is being launched on *REMOTEHOST*.
4. Add a Pseudocolor plot of *u* and a Mesh plot of *mesh1*.
5. Post the **Compute engine window** or make it visible if it is obscured.
6. Click the **Draw** button.
7. Once the parallel compute engine is launched on *REMOTEHOST*, check the **Compute engine** window to make sure that it has a compute engine on *REMOTEHOST* with 4 processors from 1 node. If the **Engine** combo box shows the compute engine for your local computer instead of the compute engine for *REMOTEHOST*, select the entry for *REMOTEHOST*. After the compute engine is launched, it will start processing the plots so you should see the progress meters in the **Compute engine** window start changing.
8. After the plots appear, open *globe.silo* from localhost

9. Create a Pseudocolor plot of  $u$
10. Click the **Draw** button and wait for the new plot to appear in the vis window. The spherical plot was generated on your Windows desktop computer and the other plots were generated in parallel on *REMOTEHOST* using data files that exist on *REMOTEHOST*.
11. Click the **Delete** button until there are no more plots in the plot list.

### Exercise group 3: Working with plots

#### Exercise 3a) Hiding a plot

1. Open the **File selection** window and make sure that the **selected files** list contains *multi\_curv2d.silo* from *REMOTEHOST*. If the selected files list does not contain *multi\_curv2d.silo*, change the host to be *REMOTEHOST*, and change the directory to the VisIt sample data directory (*/usr/gapps/visit/data*). Change your file filter to be *\*.silo*. Click the **Select all** button to add all files ending in *.silo* to the **selected files** list.
2. Open *multi\_curv2d.silo* from *REMOTEHOST*.
3. Create a Mesh plot of *mesh1* and click the **Draw** button.
4. Create a Pseudocolor plot of  $d$  and click the **Draw** button. The visualization window should contain plots that together look like a rainbow with mesh lines on it.
5. Create a FilledBoundary plot of *mat1* and click the **Draw** button. Note that the FilledBoundary plot covers up the Pseudocolor plot.
6. If you want to see the Pseudocolor plot again, you need to hide the FilledBoundary plot. Click the **Hide/Show** button to hide it.
7. Click the **Hide/Show** button a few times until at last, the FilledBoundary plot is hidden again.
8. Select both the Pseudocolor plot and the FilledBoundary plot in the **plot list**.
9. Click **Hide/Show** a few more times. Note that the *(hidden)* indicator alternates between the two plots. Alternating hidden plots in this manner is more useful in 3D because plots can sometimes occupy the same screen space and cause depth buffer conflicts if you draw them both. This way you only draw one of the plots.
10. Click the **Delete** button until all of the plots have been deleted.

#### Exercise 3b) Changing a plot's variable

Sometimes it can be a lot of effort to set up a plot with all of its operators and plot attributes. If you want to look at related variables with the same plot and keep switching back and forth, VisIt allows you to change the variable for selected plots.


1. Create a Pseudocolor plot of  $d$  from *multi\_curv2d.silo* and click the **Draw** button.

2. Change the variable to  $p$  by clicking on the  $p$  option in the **Variables** menu in the **Plot and Operator** menu bar.
3. Change the variable to  $u$  by clicking on the  $u$  option in the **Variables** menu in the **Plot and Operator** menu bar.
4. Change the variable to  $v$  by clicking on the  $v$  option in the **Variables** menu in the **Plot and Operator** menu bar.
5. Delete the plot by clicking the **Delete** button.

### Exercise 3c) Pseudocolor plot


The Pseudocolor plot maps scalar values to colors so you can easily pick out regions of interest in the data. The Pseudocolor plot is one of the most important plots in VisIt.

1. Open *multi\_rect2d.silo* on *REMOTEHOST*.
2. Create a Pseudocolor plot of  $p$ .
3. Click the **Draw** button.
4. Open the **Pseudocolor plot attributes** window.
5. Change the centering of  $p$ , which is a zone centered variable, to node centered by clicking the **Nodal** radio button and clicking the **Apply** button. Notice that the plot gets smoother. Change back to **Natural** centering when you are done.
6. Click the **Max** radio button to turn on the maximum text field. Type *10* into the maximum text field and click the **Apply** button. This makes the maximum value used in coloring the plot *10* instead of the actual maximum data value. Setting the limits can improve how colors are spread out when most values in the data cluster near the average data value.
7. Click the **Max** radio button again to turn it off and click the **Apply** button.
8. Better color mapping can also be achieved by using different data scaling. Click the **Log** radio button to use logarithmic data scaling. Click the **Apply** button.
9. Click on the **Skew** radio button to enable skew scaling. Enter a skew factor of *0.005* into the **Skew factor** text field and click the **Apply** button.
10. Skew scaling can highlight data at the low end or the high end of the data range. Type *10* into the **Skew factor** text field to highlight data with larger values. Click the **Apply** button.




user: whiffocb  
Mon Feb 16 16:27:18 2004

11. Delete the plot.
12. Open *noise.silo* on REMOTEHOST.
13. Add a Pseudocolor plot of PointVar.
14. Open the **Pseudocolor plot attributes** window.
15. Click the **Scale point size by variable** check box so point scaling is enabled.
16. Type *0.2* into the **Point size** text field.
17. Click the **Axis** radio button so points will be displayed as axis-aligned planes.
18. Click the **Color table** button and select *calewhite*.
19. Click the **Apply** button to make VisIt generate the plot.



20. Add another Pseudocolor plot. This time, use the variable *hardyglobal*.
21. Change the **opacity** of the second plot to 50% by clicking on the *Opacity slider* and decreasing the opacity until it reads 50%.
22. Click the **Apply** button.
23. Click the **Draw** button in the **Main** window to make VisIt draw the second Pseudocolor plot. Once the plot has been generated, the points from the first Pseudocolor plot should be visible inside the second plot because it was made transparent.






24. Delete both Pseudocolor plots by clicking the **Delete** button in the **Main** window until there are no more plot entries in the **plot list**.

### Exercise 3d) Mesh plot

The Mesh plot shows the mesh lines for a mesh variable.


1. Use *noise.silo*, which was opened in the previous exercise.
2. Create a Pseudocolor plot and click the **Draw** button.
3. Add a Mesh plot of *Mesh* and click the **Draw** button. Notice that the mesh lines get drawn over the Pseudocolor plot.
4. Open the **Mesh plot attributes** window.
5. Most of the time, the Mesh plot uses the vis window's foreground color. If you want to make it use another color, click the **Use foreground** check box so it gets turned off. Once you've done that, click on the **Mesh color** color button and select a new color for the mesh lines.
6. Click the **Apply** button.
7. Delete both plots.



### Exercise 3e) FilledBoundary plot


The FilledBoundary plot is for coloring a database's material subsets so it is obvious where they are located in the mesh. This exercise will familiarize you with some of the options for the FilledBoundary plot.

11. Open the **File selection** window and make sure that the **selected files** list contains *multi\_curv3d.silo* from *REMOTEHOST*. If the selected files list does not contain *multi\_curv3d.silo*, change the host to be *REMOTEHOST*, and change the directory to the VisIt sample data directory (*/usr/gapps/visit/data*). Select *multi\_curv3d.silo* from the **Files** list into the **selected files** list.
12. Open *multi\_curv3d.silo* from *REMOTEHOST*.
13. Created a FilledBoundary plot of *mat1* and click the **Draw** button.
14. Click on the **Wireframe** check box to turn on wireframe mode. Change the **Line style** to dashed and click the **Apply** button. The FilledBoundary plot will now only show the edges of the materials in the mesh as a set of wireframe lines.
15. Turn off wireframe mode and click the **Apply** button.
16. Click on the **Multiple** radio button to make sure that the plot's subsets are colored using user defined colors. Click on the color for material 1 in the **Boundaries** list and then click on the color button immediately above it. This will change the color for the highlighted subset once you click the **Apply** button. Set the colors for several material subsets and click the **Apply** button. Note that you may have to rotate the plot in the visualization window in order to see your changes. Your best bet is to change colors beginning at the bottom of the Boundaries list. You can also change the opacities independently for each subset to make some subsets more transparent than others.
17. Highlight *multi\_ucd3d.silo* in the **Selected files** list.
18. Click the Replace button to replace the FilledBoundary plot's database with *multi\_ucd3d.silo*.
19. Since the variable is a material, make the first material in the **Boundaries** list be partially transparent. This should result in the whole plot being transparent and all the same color.
20. Click the **Draw internal surfaces** check box to show the material boundaries that are internal. Click the **Apply** button.
21. Finally, change opacity of the entire plot by dialing down the **Opacity slider** to about 37%. Make the plot use the *xray* color table instead of using the user defined colors. This should produce a plot that shows a couple internal layers of transparent materials, which is a useful feature for looking at nested parts. The plot looks reminiscent of a radiograph.




### Exercise 3f) Contour plot (optional)

1. Open *noise.silo* on *REMOTEHOST*.
2. Create a Contour plot of *hardyglobal*.
3. Open the **Contour plot attributes** window.
4. Type 5 for the new **N levels** value and press Enter. This should change the number of colors in the **multiple color list** to 5.
5. Change the opacity for contour level two to 20%.
6. Change the opacity for contour level three to 30%.
7. Change the opacity for contour level four to 40%.
8. Click the **Apply** button to make VisIt generate the plot.
9. Change the plot variable to *hgslice* using the **Variable** menu in the **Plot and Operator** menu. This will change the plot to 2D.
10. Type 30 for a new **N levels** value and press Enter. This should change the number of colors in the **multiple color list** to 30.
11. Click the **Color table** radio button to make the plot use a color table for its colors.
12. Click the color table button and select the *hot* color table.
13. Click **Apply** to make VisIt regenerate the plot.



### Exercise 3g) Volume plot (optional)

1. Open the **File selection** window and make sure that the **Selected files** list contains *CThead\_mid.silo* from *REMOTEHOST*. If the selected files list does not contain *CThead\_mid.silo* from *REMOTEHOST*, change the host to be *REMOTEHOST*, and change the directory to the VisIt sample data directory (*/usr/gapps/visit/data*). Select *CThead\_mid.silo* from the **Files** list into the **selected files** list. Note that your local computer may have a copy of *CThead\_mid.silo* but you want to make sure you use the copy from *REMOTEHOST* so VisIt can process the data in parallel.
2. Open *CThead\_mid.silo* on *REMOTEHOST*.
3. Create a Volume plot of *head*.
4. Add a Box operator.
5. Open the **Box operator attributes** window.
6. Type *0.1* for **X-minimum**.
7. Type *0.75* for **X-maximum**.
8. Type *0* for **Y-minimum**.
9. Type *1.1* for **Y-maximum**.
10. Type *0.06* for **Z-minimum**.
11. Type *0.95* for **Z-maximum**.
12. Click the **Apply** button.
13. Open the **Volume plot attributes** window.
14. Change the number of sample points to *1500000*.
15. Click the **Gaussian** radio button to change to a Gaussian opacity curve.
16. Create some curves by clicking in the **opacity control**. Move the **control points** for the curves to change their shapes.
17. Change the opacity attenuation to *8%*.
18. Remove some **color control points** by clicking the “-” button. Arrange the color control points and set their colors as shown in the picture below.
19. Click the **Apply** button to make VisIt generate the Volume plot.
20. Experiment with different colors, opacity curves, and views.




### Exercise 3h) Surface plot (optional)

The surface plot shows subtle differences in value for a 2D scalar variable by incorporating the value of the variable into the height of the plot. This exercise will familiarize you with some of the options of the Surface plot.

1. Open the **File selection** window and make sure that the **selected files** list contains *noise.silo*. If the selected files list does not contain *noise.silo*, change the host to be *localhost*, and change the directory to the VisIt sample data directory (*C:\Program Files\LLNL\VisIt 1.4.1\data*). Select *noise.silo* from the **Files** list into the **selected files** list.
2. Open *noise.silo* from *REMOTEHOST* or from your desktop computer.
3. Add a Surface plot of *hgslice* and click the **Draw** button. The plot normally comes up with the Z-axis facing the camera but if you rotate the view a little with the mouse, you should be able to make the Z-axis point straight up.
4. Open the **Surface plot attributes** window.
5. Select the *calewhite* color table by clicking on the color table button next to the **Z value** radio button. Click the **Apply** button and watch the plot's colors change.
6. Click the **Constant** surface color radio button and select a new color for the Surface plot. Click the **Apply** button and watch the plot turn to a single color.
7. Click the **Wireframe** checkbox to turn on surface ruling. Click the **Wire color** button and select the color red. Click the **Apply** button and watch the surface get red lines all over it where the mesh lines lie.
8. Take turns clicking the **Linear**, **Log**, and **Skew** radio buttons for scaling. The scaling options tell the Surface plot how to map the plotted variable to height.

Make sure that when you use **Skew** scaling, you enter an interesting **skew factor** like 0.01 or 100.

9. Experiment with setting the **min** and the **max** values for the limits. Notice that when you increase the data range, by having a larger range in the limits, that the height of the surface is lessened. Having smaller limits seems to increase the steepness of the plot so if you are examining a 2D database without a lot of range in the data, you might try the Surface plot so you can easily pick up small variations in the data by detecting large changes in surface height.




### Exercise 3i) Curve plot (optional)

VisIt can read curve files, which are simple text files of X,Y pairs such as the files used by ULTRA. Curves can also be extracted from higher dimensional databases using the Lineout operator but that will be covered later. For now, we will look at opening curve files and plotting some of the curves out of them.

1. Open the **File selection** window
2. Set the host to *REMOTEHOST* if that is not the current host.
3. Make sure that */usr/gapps/visit/data/CURVE/curve.visit* gets added to your selected files list. Click **OK** to accept the new selected files list.
4. Open *curve.visit*.
5. Create a Curve plot of *parabolic*.
6. Create a Curve plot of *flat*.
7. Create a Curve plot of *going\_down*.
8. Create a Curve plot of *going\_up*.
9. Use the **Animation slider** to set the active time to 0048 so the curves will not be so straight.



10. Click the **Draw** button. VisIt should generate four curves in the visualization window.
11. Click on the Curve plot of *parabolic* in the **plot list**.
12. Open the **Curve plot attributes** window.
13. Click on the **Color** button and select red
14. Click on the **Points** check box to make the *parabolic* curve display points where the original x,y curve points are located.
15. Click the **Apply** button.
16. Click on the Curve plot of *going\_down* in the plot list.
17. Set the **Line style** to dashed and set the **Line width** to a thicker width.
18. Click on the **Color** button and select green.
19. Click the **Apply** button.
20. Change the active time back to 0000 and delete all of the Curve plots.



## Exercise group 4: Visualization windows

### Exercise 4a) Using multiple windows

It is commonplace to compare databases using multiple VisIt windows. Using multiple windows allows side by side comparison of databases so VisIt provides special features for cloning windows, copying plots, and locking windows together in time and locking views.

1. Make sure that *wave\*.silo database* from localhost is in your selected files list then open *wave\*.silo database* on your local computer.
2. Add a Pseudocolor plot of pressure.
3. Click the **Draw** button.
4. Click **View** option in the **Lock** submenu in the **Main** window's **Windows** menu. This will make the vis window's view be sent to other windows that have locked views when you change the view.
5. Click **Time** option in the **Lock** submenu in the **Main** window's **Windows** menu. This will make the vis window's time be sent to other windows that have locked time when you change the active time state.
6. Click on the **Clone window** option in the **Main** window's **Windows** menu. The **Clone window** option makes a copy of the active window, including all of its plots and view, etc. Cloning the window will make the new window be the active window. That is fine because we need to click the **Draw** button to get vis window 2's plots to generate.
7. Make vis window 1 be the active window by clicking on the **Make window active** button in the vis window's toolbar. Slowly move the mouse over the buttons in the upper left corner and tool tips will appear for the button under the mouse cursor.
8. Click the **1x2** option in the **Layout** submenu in the **Main** window's **Windows** menu. This will cause VisIt to change the sizes of both windows so they can fit side by side.
9. Rotate the plot in the first vis window. Watch the plot in vis window 2 redraw with the same view as the plot in vis window 1.
10. Change the **Animation slider** in the **Main** window to cycle 0350. Watch the plot in vis window 2 also change to cycle 0350.
11. Make vis window 2 be the active window by selecting 2 from the **Active window** combo box in the **Main** window. This will tell the viewer to make all changes to plots from vis window 2.
12. Change the **Animation slider** to cycle 0500. Watch the plot in vis window 1 also change to cycle 0500.
13. Rotate the view in vis window 2 and zoom in a little bit. Watch the plot in vis window 1 redraw with the same view as the plot in vis window 2.
14. Delete window 2 by dismissing it using the Windows window decorations in the frame around the vis window. VisIt will make vis window 1 be the active window again.

## Exercise 4b) View manipulation

VisIt has some special view features that MeshTV did not have. The first one that you will use in this exercise is *Save view*. *Save view* allows you to save the current view to a toolbar button that you can press later. You can save up to 16 views and switch between them using a single button click. These views can even be saved to your VisIt configuration settings for use in later VisIt runs. The second view feature that you will



use in this exercise is *Undo view*. *Undo view* lets you return to your last view if you make a mistake. You can undo up to 16 view changes.

1. Use the plots from the previous exercise.
2. Locate the **Save view** toolbar button in the **View** toolbar and click it. You can also click **Save view** under the **View** menu in the **popup** menu, which you can activate by right-clicking in the vis window.
3. Once you click the **Save view** button, a new icon with a 1 should appear in the toolbar and the popup menu. If you click on that button, VisIt uses the view that you currently have set.
4. Rotate the plot in the vis window.
5. Click **Save view** again. This should create a new button with a 2 in it.
6. Zoom in on the Pseudocolor plot.
7. Click **Save view** again. This should create a new button with a 3 in it.
8. Click the saved view 1 button.
9. Click the saved view 2 button.
10. Click the saved view 3 button.
11. Zoom in on the plot some more. Let's pretend that you zoomed in accidentally. If you want to undo the zoom, click the **Undo view** button in the toolbar or the popup menu.
12. Delete the Pseudocolor plot.

### Exercise 4c) Special 2D view manipulation

Vis windows have several modes. The default mode is navigation mode, which allows you to rotate and translate plots to get a nice view of them. Another important mode is zoom mode. When a vis window is in zoom mode, you can click in the window and sweep out rectangles to zoom in on.

1. Open *curv2d.silo* on your desktop computer.
2. Create a Pseudocolor plot of  $u$ .
3. Create a Mesh plot of *curvmesh2d*.
4. Click the **Draw** button.
5. Switch the vis window into zoom mode by clicking on the magnifying glass button in the vis window's toolbar.
6. Click on the plot and sweep out a zoom rectangle that you would like to see in more detail. If you don't like the rectangle that you zoomed in on, remember that you can click the **Undo view** toolbar button.
7. Zoom in a few times by drawing zoom rectangles.
8. Click the **Reset view** toolbar button to switch to the original view for the plots.
9. Hold down the Shift key and sweep out a zoom rectangle. Note that the rectangle is constrained to be square when you hold down the Shift key.
10. The plots from the current database do not make much use of the vis window's area because they are relatively long and skinny. For plots with this kind of aspect ratio, VisIt provides a Full frame mode, that stretches the plots so they take up

more of the vis window. The scaling is not uniform in the X and Y dimensions but it does get the plots to take up more space. Put the vis window in Full frame mode by clicking on **Fullframe** in the popup menu's **View** menu.

11. When you are done, turn off Full frame mode since it is not required for future exercises.
12. Switch the vis window back into navigate mode.
13. Delete the plots.

## Exercise group 5: Working with operators


### Exercise 5a) Slice operator

This exercise teaches you how to add an operator and change some of its attributes and make those attributes be the default attributes for the operator.

1. Open *noise.silo* on your local computer.
2. Create a Pseudocolor plot of *hardyglobal* and click the **Draw** button.
3. Add a Slice operator.
4. Open the **Slice operator attributes** window.
5. Turn off the **Project to 2D** check box.
6. Click the **Orthogonal Z axis** radio button to make the slice plane's normal be along the Z axis.
7. Click on the **Percent** radio button in the **Origin** group and set the **Percent** to be 50. This will create a slice plane that is 50% of the way through the data along the Z axis.
8. Click the **Apply** button.
9. Click the **Make default** button to make these slice attributes be the default slice attributes for all future slices. If VisIt asks you if you really want to make these slice attributes be the default slice attributes, click the **Ok** button.
10. Delete the Pseudocolor plot
11. Add a FilledBoundary plot of *mat1* and click the **Draw** button.
12. Add a Slice operator


The new FilledBoundary plot should have the same slice plane as your Pseudocolor plot had. If you have not modified your 3D view settings, the picture should look like this:

13. Project the slice to 2D by clicking on the



**Project to 2D** check box.


- Click the **Apply** button. The plot should now be 2D but the data in the slice will look the same as before.




## Exercise 5b) Reflect operator

The Reflect operator is useful for displaying the full geometry of a simulation if only half or a quarter of it was simulated due to problem symmetry. The Reflect operator can also be used in this manner to display plots of multiple types when recreating the full geometry through reflection.

- Open *multi\_curv2d.silo* on your local computer.
- Create a FilledBoundary plot of *mat1*.
- Create a Pseudocolor plot of *u*.
- Click the **Draw** button. Only the Pseudocolor plot will be visible.
- Turn off the **Apply operators and selection to all plots** check box in the **Main** window because we are going to apply the Reflect operator to only the Pseudocolor plot.




6. Open the **Reflect operator attributes** window.
7. Click on the magenta ball to turn off the data in that quadrant. In this case, we only want the data from quadrant 1, which is where the data is located, to be reflected into quadrant 4. This will allow us to have the FilledBoundary plot on top and have the Pseudocolor plot on bottom. This is a common configuration in some movies made at the Lab.
8. Click the **Apply** button and click the **Yes** button when VisIt asks if you want to apply the Reflect operator.
9. Try turning on some other quadrants to see what happens.
10. Turn on the **Apply operators and selection to all plots** check box in the **Main** window.
11. Delete both plots.



### Exercise 5c) Clip operator

The Clip operator clips out regions of a plot using either planes or a sphere as the clipping surface. The resulting plot retains its original dimension. The clip operator is good for being able to see into the interior of a 3D plot. The Clip operator is useful in animations where you remove a wedge of a 3D plot and then move it out to see the inside of the plot.

1. Open the **File selection** window.
2. Make sure that *localhost* is the host where you're looking for files.
3. Type *C:\Program Files\LLNL\VisIt 1.4.1\data* into the **Path** text field and press the Enter key.
4. Change your filter so you can see all files by typing *\** into the **Filters** text field. Press the Enter key for it to take effect.
5. Click the **Remove all** button to clear out the files in the **selected files** list.
6. Click the **Select all** button to add all files with to the **selected files** list.
7. Open *globe.silo*.
8. Create a Pseudocolor plot of *speed*.
9. Create a Mesh plot of *mesh1*.
10. Click the **Draw** button.
11. Add a Clip operator. Note that both plots are regenerated and when they reappear, both only have half of the geometry that they once had.
12. Open the **Clip operator attributes** window.
13. Turn on clipping plane 2 by clicking on the **On** radio button in the **Plane 2** settings. Click the **Apply** button in the **Clip operator attributes** window.
14. Turn on clipping plane 3 by clicking on the **On** radio button in the **Plane 3** settings. Click the **Apply** button in the **Clip operator attributes** window. At this point, roughly  $1/8^{\text{th}}$  of the plots should be removed, giving you a window into the center of the plots. Clipping planes can have any orientation but the planes in this example are axis-aligned.
15. Click on the **Sphere tab** in the **Clip operator attributes** window. This will cause VisIt to clip using a sphere.
16. Type *10 10 10* into the **Center** text field.
17. Type *10* into the **Radius** text field.
18. Click the **Apply** button. This will cause the plot to be clipped by a sphere, centered at *(10, 10, 10)* with a radius of *10*.
19. Type *8* into the **Radius** text field, type *5 5 5* into the **Center** text field and click the **Apply** button. This will cause the plots to be clipped by a sphere centered at *(5, 5, 5)* with a radius of *8*.
20. Click the **Inverse** check box and click the **Apply** button. This will make the clip operator keep the parts of the plot that it used to throw away, while throwing away the parts that it used to keep.
21. Delete both plots.



### Exercise 5d) Onion Peel operator

The Onion Peel operator is useful for zoning in on a particular cell in a database. For example, you might be looking for the cell that you know has the highest value. You might also be debugging a simulation code that told you there was a problem with a specified cell.


#### Simple case

1. Use *globe.silo* from the previous exercise.
2. Create a Pseudocolor plot of *speed*.
3. Create a Mesh plot of *mesh1*.
4. Click the **Draw** button.
5. Open the **Onion Peel operator attributes** window. Pretend that your simulation code told you there was a problem with cell *10* in this unstructured mesh.
6. Type *10* into the **Cell # or ij[k]** text field.
7. Click the **Apply** button and answer **Yes** when VisIt asks you if you want to add an Onion Peel operator.
8. Change the layers to be *1* and click **Apply**. This will give the original cell (cell 10) and all of its immediate neighbors.
9. Change the layers to be *2* and click **Apply**. This will give the original cell (cell 10) and all of its neighbors within 2 layers.
10. Delete both plots.

#### Multiple domain case

1. Open *multi\_rect3d.silo* on your local computer.
2. Create a Pseudocolor plot of *d*.
3. Create a Mesh plot of *mesh1* and click the **Draw** button.
4. Add an Onion Peel operator. This should force VisIt to regenerate the plots. When the image in the visualization window changes, there should be a single cell from domain 1.

5. Suppose that we are only interested in cell  $ijk$  (5,5,5) in domain 7. Select domain 7 from the **Set list** in the **Onion Peel operator attributes** window.
6. Type 5 5 5 into the **cell # or ij[k]** text field.
7. Click the **Apply** button. VisIt will now produce an image that shows only one cell (cell 5,5,5 from domain 7).
8. Click the **Face** radio button so layers are grown out only if they share faces with previous layers.
9. Change the layers to be 2 and click the **Apply** button.
10. Grow out more layers by incrementing the value in the **Layers** text field a few times. Don't forget to click the **Apply** button.
11. Delete both plots.



## Exercise 5e) Transform operator (optional)

The Transform operator is commonly used to change the scale or orientation of one database so it can be added to the same vis window as another database for comparison purposes. In this exercise, we will create a Contour plot of a skull database and use the Transform and Clip operators to position a brain from an unrelated database inside the skull!

*Note: This exercise should be performed using a parallel compute engine on REMOTEHOST since some stages of this exercise require more resources than are typically found on a desktop workstation.*

1. Open the **File selection** window.
2. Make sure that *REMOTEHOST* is the host where you're looking for files.
3. Type `/usr/gapps/visit/data` into the **Path** text field and press the Enter key.

4. Change your filter so you can see all files by typing \* into the **Filters** text field. Press the Enter key for it to take effect.
5. Click the **Remove all** button to clear out the files in the **Selected files** list.
6. Click on *CThead\_mid.silo* in the **Files** list and click the **Select** button to add *CThead\_mid.silo* to the **Selected files** list.
7. Browse into the *ANALYZE* directory by either typing:  
*/usr/gapps/visit/data/ANALYZE* into the **Path** text field or by double-clicking the *ANALYZE* directory.
8. Click on *s01\_anatomy\_stripped.img* and click the **Select** button to add that file to the **Selected files** list.
9. Click **OK** to accept the new list of selected files.
10. Open *CThead\_mid.silo*.
11. Add a Contour plot of the *head* variable.
12. Open the **Contour plot attributes** window and change the **Select by** to be **Value(s)**. Type the value: 25 into the text field next to **Select by** and press the Enter key. This will create a single contour for the value 25 in the data range and the multiple color list will update to have a single color. Set the color to white.
13. Click the **Apply** button in the **Contour plot attributes** window.
14. Add a Clip operator to the Contour plot.
15. Open the **Clip operator attributes** window
16. Set the attributes for plane 1. Type: 0.42 0 0 into the **Origin** text field. Type: -1 0 0 into the **Normal** text field. Turn plane 1 on.
17. Set the attributes for plane 3. Type: 0.42 0 0.4 into the **Origin** text field. Type 0 0 -1 into the **Normal** text field. Turn plane 3 on.
18. Click the **Apply** button in the **Clip operator attributes** window.
19. Click the **Draw** button to make VisIt generate the skull plot in parallel on *REMOTEHOST*.


Here are the instructions for the brain transplant using the Transform operator.

1. Open *s01\_anatomy\_stripped.img*.
2. Turn off the **Apply operators and selections to all plots** check box in the **Main** window. We have to do this because we are going to add multiple Transform operators and if that flag is on then both transforms will get the operator attributes that we set later.
3. Add a Contour plot of *Variable*.
4. Open the **Contour plot attributes** window and change the **Select by** to be **Value(s)**. Type the value: 38 into the text field next to **Select by** and press the Enter key. This will create a single contour for the value 38 in the data range and the multiple color list will update to have a single color. Set the color to be rose.
5. Expand the new Contour plot entry in the plot list.
6. Add a Transform operator using the **Operators** menu.
7. Open the **Transform operator attributes** window and turn on rotation by clicking the **Rotation** check box. Type: 0 1 0 into the **Axis** text field. Type: 90 into the **Amount** text field and make sure that the **Deg** radio button is set so that we are entering a rotation of 90 degrees about the Y-axis.



8. Add another Transform operator using the **Operators** menu.
9. Turn on rotation by clicking the **Rotation** check box. Type: *1 0 0* in the **Axis** text field. Type: *90* into the **Amount** text field and make sure that the **Deg** radio button is set so that we are entering a rotation of 90 degrees about the X-axis.
10. Turn on scaling by clicking the **Scale** check box. Type *0.0021* for the **X** scaling text field. Type *0.00195* for the **Y** scaling text field. Type *0.00195* for the **Z** scaling text field.
11. Turn on translation by clicking the **Translate** check box. Type *0.41* for the **X** translation text field. Type *0.53* for the **Y** translation text field. Type *0.355* for the **Z** translation text field.
12. Click the **Apply** button to apply the new Translate operator attributes to the second Translate operator.
13. Click the **Draw** button to start generating the brain on *REMOTEHOST*. This plot will not be generated quite as fast as the skull because it is a somewhat larger database than the skull and it is not domain decomposed so VisIt cannot generate the plot in parallel.

The resulting plots should look something like this:




### Exercise 5f) Index select operator (optional)

The index select operator allows you to resample your data down to fewer cells. The Index select operator also you select out a rectangular brick of cells.

#### Resampling


1. Open *noise.silo* on your local computer.
2. Create a Pseudocolor plot of *radial*.
3. Create a Mesh plot of *Mesh*.
4. Click the **Draw** button.

5. Turn on the **Apply operators and selection to all plots** check box in the **Main** window if it is not turned on since we want the Index select operator to apply to both plots.
6. Open the **Index select operator attributes** window.
7. Click the **3D dimension** radio button because the plots to which we're applying the operator are 3D.
8. Type  $0:max:2$  into the top **Min,max,incr** text field, which is for selecting the cell indices for the X dimension. We're telling the operator to take every other cell.
9. Type  $0:max:4$  into the middle **Min,max,incr** text field, which is for selecting the cell indices for the Y dimension. We're telling the operator to take every 4<sup>th</sup> cell.
10. Type  $0:max:8$  into the bottom **Min,max,incr** text field, which is for selecting the cell indices for the Z dimension. We're telling the operator to take every 8<sup>th</sup> cell.
11. Click the **Apply** button in the **Index select operator** window and click the **Yes** button when VisIt asks whether you want to apply the Index select operator.  
When VisIt is done regenerating the plots, the X dimension should have  $\frac{1}{2}$  the cells, the Y dimension should have  $\frac{1}{4}$  the cells, and the Z dimension should have  $\frac{1}{8}$  the cells that it originally had.



#### Extracting a brick of cells

1. Use the current plots and Index select operator.
2. Type  $10:30:1$  into the top **Min,max,incr** text field.
3. Type  $10:20:1$  into the middle **Min,max,incr** text field.
4. Type  $10:15:1$  into the bottom **Min,max,incr** text field.
5. Click the **Apply** button.
6. Delete both plots.



### Exercise 5g) Threshold operator (optional)


The Threshold operator removes cells that do not have values that fall within the desired range. This exercise will show you how to remove cells by thresholding using the plotted variable and by thresholding using another database variable.

Threshold using the plotted variable

1. Open *noise.silo* on your local computer if it is not already open.
2. Create a Pseudocolor plot of *hardyglobal*.
3. Click the **Draw** button.
4. Open the **Threshold operator attributes** window.
5. We want to find the cells in the plot that have high values for the plotted variable so type 5.5 into the **Lower bound** text field. This will cause VisIt to throw out all cells that don't have nodes that have values higher than 5.5.
6. Click the **Apply** button in the **Threshold operator attributes** window.

Threshold using another variable


1. Sometimes it use useful to see the values for the plotted variable but select cells based on the value of another variable. The Threshold operator usually uses default, which evaluates to the plotted variable but if you want to threshold using another variable, you can do that. Let's show the plotted variable but only for cells whose chrome material volume fraction is at least 0.75.
2. Type 0.75 into the **Lower bound** text field.
3. Type *chromeVf* into the **variable** text field. The *chromeVf* variable is another variable in the *noise.silo* database that contains the chrome material's volume fraction in each cell.
4. Click the **Apply** button.



### Exercise 5h) Isosurface operator (optional)

The Isosurface operator lets you create contours of one variable while coloring the plot by another variable. In this example, we will display a variable while contouring by a material volume fraction.


1. Open *noise.silo* on your local computer if it is not already open.
2. Create a Pseudocolor plot of *hardyglobal*.
3. Click the **Draw** button.
4. Open the **Isosurface operator attributes** window.
5. Change **Select by** to be **Value(s)** and type in a value of *0.7*.
6. Type *chromeVf* into the **variable** text field. We are going to create a single isosurface with a value of *0.7* in the *chromeVf* variable. This has the effect of contouring by a material volume fraction since *chromeVf* is the volume fraction of the chrome material in each cell.
7. Click the **Apply** button.
8. Delete the plot.



### Exercise 5i) Box operator (optional)

The Box operator selects cells that lie within an axis-aligned box and removes all other cells from plots to which the Box operator is applied.

1. Open *noise.silo* on your local computer if it is not already open.
2. Create a Pseudocolor plot of *hardyglobal*.
3. Click the **Draw** button.
4. Open the **Box operator attributes** window.
5. Let's extract only those cells that are in a box whose origin is at  $(0,0,0)$  and measures 7 on each side.
6. Type 7 into the **X-Maximum** text field.
7. Type 7 into the **Y-Maximum** text field.
8. Type 7 into the **Z-Maximum** text field.
9. Click the **Apply** button.
10. Delete the plot.




### Exercise 5j) Cone operator (optional)

The Cone operator slices 3D plots with a cone and it can either leave the slice in 3D or it can unravel the cone into a 2D projection of the cone to make checking for radial symmetry easy.

1. Open *multi\_rect3d.silo* on your local computer.
2. Create a Pseudocolor plot of *d*.
3. Click the **Draw** button.
4. Open the **Cone operator attributes** window
5. Type 25 into the **Angle** text field. The angle is specified in degrees.
6. Type 0.5 0 0.5 into the **Origin** text field. The origin is the point of the cone.
7. Type 0 1 0 into the **Direction** text field. We want a cone that points straight down so we entered 0 1 0, which is the Y-axis.
8. Finally, we want to project the plot to 2D so we can check symmetry. Click the **Projected to 2D** radio button.
9. Click the **Apply** button and answer **Yes** when VisIt asks you to apply the operator. Note that you might need to reset the view in order to see the plot.
10. To reset the view, right click the mouse in the **visualization window** and choose **View->Reset view** in the **popup** menu.





### Exercise 5k) Inverse ghost zone operator (optional)

The inverse ghost zone operator is useful for finding out if your database has ghost zones, which are zones at domain boundaries that are normally not displayed and used internally for such purposes as producing smooth Contour plots.

VisIt is distributed with the Inverse ghost zone operator but it is not enabled by default. In order to do this exercise, you must enable the Inverse ghost zone operator, which will require you to restart VisIt.


Enabling the Inverse ghost zone operator:

1. Open the **Plugin Manager** window using the **Options->Plugin Manager** menu option.
2. Click on the **Operators** tab
3. Click on the checkbox next to the Inverse ghost zone operator to enable it.
4. Dismiss the **Plugin Manager** window
5. Save your settings by clicking on the **Options->Save settings** menu option.
6. Quit VisIt
7. Start VisIt
8. The Inverse ghost zone operator should be listed in the **Operators** menu.

Using the Inverse ghost zone operator:

1. Open the **File selection** window.
2. Change the host to *REMOTEHOST*.
3. If the path is not set to */usr/gapps/visit/data* then change to that path.
4. Clear out the **selected files** list by clicking the **Remove all** button.
5. Change the filter to be *\*.silo* so all files ending in *.silo* are available.

6. Click the **Select all** button so all files in the **Files** list are added to the **selected files** list.
7. Click **OK** to accept the new **Selected files** list and dismiss the **File selection** window.
8. Open *multi\_ucd3d.silo*.
9. Create a Pseudocolor plot of *d*.
10. Create a Mesh plot of *mesh1*.
11. Click the **Draw** button.
12. Add an Inverse ghost zone operator.
13. Delete the plot when you are done.




### Exercise 5I) ThreeSlice operator (optional)

The ThreeSlice operator computes three axis-aligned slice planes that converge at a point. The ThreeSlice operator is a nice, quick way to see inside 3D plots. In this exercise, we will examine the contents of a CT scan of a head using the ThreeSlice operator.

1. In the previous exercise, you selected files from *REMOTEHOST*. We will use files from that computer again in this exercise. Open *CThead\_mid.silo*.
2. Create a Pseudocolor plot of *head*.
3. Open the **Pseudocolor plot attributes** window and make the plot use **Skew** scaling with a **Skew factor** of *0.005*. Be sure to click the **Apply** button in the **Pseudocolor plot attributes** window for the new scaling to take effect.
4. Add a ThreeSlice operator to the Pseudocolor plot.
5. Open the **ThreeSlice operator attributes** window.
6. Type *0.42* into the **X** text field.
7. Type *0.6* into the **Y** text field.
8. Type *0.5* into the **Z** text field.



9. Click the **Apply** button in the **ThreeSlice operator attributes** window.
10. Click the **Draw** button to make VisIt draw the plot.
11. Do not delete the plot. Will use it in the first exercise in the next exercise group.



## Exercise group 6: Interactive tools

### Exercise 6a) Point tool

The point tool lets you move a point around the vis window. Some plots and operators use the point tool's information to set their attributes. In the exercise for the ThreeSlice operator in the last exercise group, we created a plot that gets sliced with the ThreeSlice operator. The ThreeSlice operator's attributes can be set using the Point tool so we are going to turn on the Point tool in this exercise and move the origin of the ThreeSlice operator from the last exercise. If you have not done exercise 5l, do it now.

1. Turn on the point tool by clicking on the **Point tool** button in the **Tools** toolbar. This should make the point tool's hot point visible.
2. Move your mouse into the point tool's hot point, click with the left mouse button, and drag the hot point to the left and release the mouse button. Once you release, VisIt sets the origin for the ThreeSlice operator and regenerates the plot.
3. Repeat step 2 but first hold down the Shift key before you click inside the point tool's hot point. Move the mouse up and down to move the point tool in the direction of the axis that most faces the camera. Moving up moves backwards and moving the mouse down moves the point tool forwards.


4. Rotate the plot using the mouse. Rotation is done the same as it usually is if you keep the mouse outside of the point tool's hot point.
5. Move the point tool some more and get comfortable with moving it around.
6. You can move the point tool in the plane that most faces the camera if you hold down other modifier keys. Holding down the Ctrl key moves the point tool up and down as you move the mouse up and down. Holding down both Shift and Ctrl keys moves the point tool left and right as you move the mouse left and right.

## Exercise 6b) Plane tool with multiple windows

The plane tool allows you to interactively position a slice plane or plane source for the Streamline plot. In this example, we will use the Pseudocolor plot from the previous exercise but we will apply a Slice operator to it instead of a ThreeSlice operator. Then we will use the plane tool to set the slice plane used for the Slice operator.

1. In previous exercises, you created a Pseudocolor plot from *CThead\_mid.silo* and applied a ThreeSlice operator to it. We will use that same plot for this exercise.
2. Remove the ThreeSlice operator from the Pseudocolor plot by either expanding the plot and clicking the operator delete "X" button or by clicking the **Remove last operator** option in the Operators menu.
3. Open the **Slice operator attributes** window
4. Click on **Orthogonal X Axis** radio button since we want to initially slice along the X axis.
5. Click on the **Point** radio button since we want to slice at a point. Next, type *0.42 0.5 0.5* into the **Point** text field.
6. Type *0 0 -1* into the **Up Axis Direction** text field. If the **Up Axis Direction** text field is not enabled, skip this step.
7. Turn off the **Project to 2D** axis check box.
8. Click the **Apply** button and answer **Yes** when VisIt asks you to apply the Slice operator.
9. Turn on the plane tool by clicking on the **Plane tool** button in the **Tools** toolbar.
10. Now try locking tools. When you lock tools, changing a tool in one window sends the new tool attributes to other windows that have also locked their tools. This will allow us to interactively move a slice plane in the first window and have it affect other windows. To lock tools for the window, click on the **Main** window's **Windows** menu option. Then click on the **Lock** submenu under the **Windows** menu. Finally, click on the **Tools** option in the **Lock** submenu.
11. Switch to the 1x2 window layout by clicking on the **Main** window's **Windows** menu option, and clicking on the **1x2** option under the **Layouts** submenu. This will cause VisIt to create a copy of the first visualization window and then resize both windows so they can be placed side by side. Note that the new window gets the plots and lock setting from the first window.
12. Make vis window 2 be the active vis window.
13. Open the **Slice operator attributes** window if you dismissed it.

14. Turn on the **Project to 2D** check box for the Slice operator. This will only apply to the Slice operator in vis window 2.
15. Move the plane tool in vis window 1 along its normal axis by clicking in its **Normal translation** hot point and moving the mouse up or down. When you move the slice plane now, both windows should update because their tools are locked.
16. Experiment with the plane tool by moving various hot points and watch both visualization windows update.
17. When you are done, delete the second vis window and switch to a 1x1 window layout so vis window 1 is again full size.




### Exercise 6c) Plane tool with multiple plots (optional)

Interactive tools can be used to set the attributes for one plot of many plots in the plot list. In this example, you will learn how to set the slice plane attributes for one plot and not another using the plane tool.

1. This example uses the sliced Pseudocolor plot from the last exercise but it also requires you to create another plot. Add a new Pseudocolor plot of *head*.
2. Open the Pseudocolor plot attributes window and make the new Pseudocolor plot use the *calewhite* color table instead of the *hot* color table. This will make the plots easier to tell apart.
3. Turn off the **Apply operators and selection to all plots** check box in the **Main** window since that toggle would interfere with the upcoming instructions.
4. Apply a Slice operator to the new Pseudocolor plot.
5. Open the **Slice operator attributes** window.
6. Turn off the **Project to 2D** check box and click **Apply**.
7. Click the **Draw** button.
8. Now there should be two sliced Pseudocolor plots in the vis window.

9. Move the plane tool. This should set the slice attributes for the second Pseudocolor plot.
10. Click on the first plot entry in the plot list so only the first Pseudocolor plot is selected. This should cause the plane tool to reset to that plot's slice plane.
11. Move the plane tool and watch the first Pseudocolor plot update.
12. Switch the plot selection a few times in the plot list and move the plane tool until you get the hang of how it works to set the slice attributes for individual plots.



## Exercise group 7: Subsets


This exercise group focuses on the Subset window and using it to remove subsets from plots.

### Exercise 7a) Material selection

This exercise focuses on material selection, which is when you remove materials from a plot.

1. Open the **File selection** window and add all of the files that end in *.silo* on your local computer in the *C:\Program Files\LLNL\VisIt 1.4.1\data* directory to the selected files list.
2. Click the **OK** button to accept the new selected files list.
3. Open *rect3d.silo* from your local computer.
4. Create a FilledBoundary plot of *mat1*.


5. Click the **Draw** button.
6. Open the **Subset** window by clicking on the **Subset** icon in the plot entry or by clicking on **Subset ...** in the **Main** window's **Controls** menu. The window will show the name of the mesh (*quadmash3d*) on which the material variable *mat1* is defined.
7. Click on *mat1* to show the material subsets in the window's middle pane.
8. Turn off the material 2 subset by clicking on its check box and clicking the **Subset** window's **Apply** button.
9. Turn off the material 4 subset by clicking on its check box and clicking the **Subset** window's **Apply** button.
10. Now reverse the material selection by clicking on the middle pane's **All sets Reverse** button. The **All sets Reverse** button turns on subsets that are off and vice-versa for all sets.
11. Make sure that the **Apply operators and selection to all plots** check box in the **Main** window is still off.
12. Add a Mesh plot of *quadmash3d* and click **Draw**. The new plot should have the same subsets selected as the first plot.
13. Click the **All sets Reverse** button in the middle pane of the **Subset** window to reverse the selection (SIL restriction) for all of the Mesh plot's subsets. Click the **Apply** button. The colored surfaces for the FilledBoundary plot should now never be obscured by any mesh lines since they have opposite SIL restrictions.



## Exercise 7b) Domain selection

This exercise focuses on domain selection, which is when you remove domains from a plot so they are not processed or drawn in the visualization.

1. Open *tire.silo* on your local computer.
2. Create a Subset plot of *domains*.
3. Create a Mesh plot of *tire* and click the **Draw** button.
4. Open the **Subset** window. Since the *tire.silo* database has both domain and material subsets, there are two subset categories under *tire*, which is the mesh that is comprised of the domain and material subsets.
5. Make sure that the **Apply operators and selection to all plots** check box in the **Main** window is still off.
6. Select both plot entries in the **plot list**.
7. Click on the *domains* category in the **Subset** window. This should cause the middle pane of the **Subset** window to be filled with a list of the database's domain subsets.
8. Turn off the *domain1* subset by clicking on its check box. Click the **Apply** button. The *domain1* subset for both plots should go away because, although the **Apply operators and selection to all plots** check box is off, we have selected both plots in the plot list and the **Subset** window sets the SIL restriction for the selected plots if the afore-mentioned check box is off.
9. Select the plot entry for the Subset plot in the **plot list**.
10. Turn off the *domain 2* subset and click the **Apply** button. Note that it only turned off the *domain 2* subset for the first plot.
11. Turn on the **Apply operator and selection to all plots** check box in the **Main** window.
12. Turn on the *domain 1* subset and click **Apply**. Notice that *domain 1* turns on and both plots now get the same SIL restriction.






## Exercise 7c) Selections involving more than one category

The Subset window allows you to turn on subsets using more than one subset category. This capability lets you turn off both domains and materials at the same time or perhaps turn off material 2 in domain 1. This exercise will show you how to set a plot's SIL restriction using more than one subset category.


1. Use the plots left over from the previous exercise and open the **Subset** window again if you closed it.
2. Click on the check box next to the *tire* subset in the first panel to turn on all subsets.
3. Click on the *domains* category under *tire* in the first panel. This will cause the *domain* subsets to be listed in the middle panel.
4. Turn off the *domain1* subset.
5. Turn off the *domain4* subset
6. Click on the green triangle to the left of the *domain4* subset. This will expand the *domain4* subset and show remaining categories that can be selected. The only option will be *Materials*.
7. Click on the *Materials* category under the *domain4* subset. This will cause the materials for the *domain4* subset to be listed in the third panel.
8. Turn on the *domain4*, 2 *Steel* and *domain4*, 3 *Cord* material subsets.
9. Click the **Apply** button.



## Exercise 7d) Practice creating more complex SIL restrictions


This exercise will give you more practice with creating SIL restrictions.

1. Use the plots from the previous exercise but change the SIL restriction so the image looks like the following image:




2. Delete both of the previous plots.
3. Open *multi\_curv2d.silo*.
4. Create a Pseudolor plot of *d*.
5. Create a Mesh plot of *mesh1*.
6. Create a FilledBoundary plot of *mat1*.
7. Click the **Draw** button.
8. Set the SIL restriction for each plot until your image looks like this:





9. Change the colors for the FilledBoundary plot to rose, yellow, and lavender.
10. Change the SIL restriction for all plots until your image looks like this:




## Exercise group 8: Quantitative Analysis

### Exercise 8a) Creating expressions

VisIt provides powerful expressions that allow you to create new variables derived from values stored in your database. This exercise focuses on creating a few expressions using values stored in a database and plotting them.

1. Delete any plots that may be in the plot list.
2. Open *rect2d.silo* on your local computer.
3. Open the **Expression** window by selecting the **Expressions ...** option from the **Main** window's **Controls** menu.
4. Click the **New** button to create a new blank expression. Change the name of the new expression to *log\_p*. Change the definition of the new expression to  $\log(p)$ .
5. Click the **New** button to create a new blank expression. Change the name of the expression to *scaled\_log\_p*. Change the definition of the new expression to  $(\log_p / 1.626) * 2. * 3.14159$ . *Tip: don't put a period after the 3.14159 when you define your expression.*
6. Click the **New** button to create a new blank expression. Change the name of the expression to *xc*. Change the definition of the new expression to  $\cos(\textit{scaled\_log\_p})$ .
7. Click the **New** button to create a new blank expression. Change the name of the expression to *yc*. Change the definition of the new expression to  $\sin(\textit{scaled\_log\_p})$ .
8. Click the **New** button to create a new blank expression. Change the name of the new expression to *newvec*. Change the definition of the new expression to  $\{xc, yc\} * 0.25$ . Set the expression type to *Vector Mesh Variable*.
9. Create a Pseudocolor plot of *scaled\_log\_p* and click the **Draw** button.
10. Create a Vector plot of *newvec*.
11. Open the **Vector plot attributes** window.
12. Click on the **Constant** color button so all vectors will be the same color.
13. Type *0.18* into the **Scale** and **Head size** text fields.
14. Click on the **Stride** radio button and make sure the stride is *1* so all vectors are shown.
15. Click the **Draw** button to make VisIt plot the new vector variable that we created from a few other derived variables.



user: whitlocb  
Sun Feb 15 19:04:12 2004

## Exercise 8b) Pick

VisIt's pick mode allows you to inspect the values for any node or zone in the visible plots by clicking on the nodes or cells that you want to know about. Pick works for 1D, 2D, and for 3D meshes and the variables defined on them but in this exercise, we will focus on 2D picking.

1. Open *noise.silo* on your local computer.
2. Create a Pseudocolor plot of *hgslice*.
3. Create a mesh plot of *Mesh2D*.
4. Click the **Draw** button.
5. Switch the vis window to node pick mode, which finds the closest node to any place that you click in the window and return the important information for that

- node. To switch into node pick mode, click on the **Node pick** button in the **Mode** toolbar or click on **Node pick** in the **popup** menu's **Mode** submenu.
6. Click somewhere on the plots in the vis window. VisIt's **Pick** window will appear with information about the pick point that is drawn in the vis window. The information will be about the Mesh plot since that is the plot that is selected in the plot list.
  7. Select the Pseudocolor plot in the **plot list**.
  8. Click somewhere on the plots in the vis window. The **Pick** window will display more information but this time the information will contain values for the *hgslice* variable since the Pseudocolor plot is selected. In general, select the plot for which you want pick information.
  9. Since *Mesh2D* is a structured mesh, it would be nice if VisIt would display the logical node indices of the node that we picked.
  10. Open the **Pick** window if it is not already open.
  11. Click on the **Domain-Logical Coords** check box for both nodes and zones and click the **Apply** button.
  12. Perform some more picks in the visualization window. The new pick information will contain the logical cell and node indices.
  13. Switch the vis window into zone pick mode.
  14. Perform some more picks in the vis window. The new pick information will contain the values for all nodes in the cell that you picked since *hgslice* is a nodal variable.
  15. Now since there are undoubtedly many pick points in the vis window, clear the pick points by choosing **Clear pick points** from the **popup** menu's **Clear** menu.

### Exercise 8c) Lineout

Lineout creates a curve by sampling values along a line and then using the values to plot a curve in another vis window. When you put a vis window in lineout mode, any line that you draw ends up generating a new curve. VisIt's lineout mode can only draw lines on 2D plots but there are other ways to create lineout curves for 3D data. This exercise will focus on 2D data.

1. Use the plots from the previous exercise.
2. Put the vis window into lineout mode using the **Mode** toolbar or the mode options in the **popup** menu.
3. Draw a line across the Pseudocolor plot of *hgslice*.
4. VisIt will open a new vis window and plot a curve in it. The curve was created by extracting the data along the line that you drew.
5. Select the **1x2** window layout so both windows can be put side by side.
6. Draw more lines to create more curves.
7. Choose **Clear reference lines** from the popup menu's **Clear** menu to clear all of the reference lines in vis window 1.
8. Switch vis window 1 back into navigate mode.

## Exercise 8d) Queries

VisIt provides a **Query** window that allows you to query values that can be calculated about a database. The **Query** window can also be used to precisely position pick points and lineouts.

1. Use the plots from the previous exercise.
2. Open the **Query** window by clicking the **Query...** option in the **Main** window's **Controls** menu.
3. Highlight the **2D area** query in the **Queries list** and click the **Query** button to make VisIt calculate the surface area for the currently selected plot in the **plot list**. The answer gets printed to the **Query results** text box in the **Query** window.
4. Highlight the **WorldPick** query in the **Queries list**.
5. Type `-4.3 4.78` into the **Query point** text field and then press the **Query** button. This causes VisIt to add a zone pick point at the specified point.
6. Highlight the **WorldNodePick** in the **Queries list**.
7. Type `-3.6 3.6` into the **Query point** text field and press the **Query** button. This causes VisIt to return pick information for the node nearest the specified point. Again, the query results are printed in the **Query results** text box.
8. Highlight the **Lineout** query in the **Queries list**.
9. Type `-8.5 8.2 0` into the **Start point** text field.
10. Type `8.6 -9.3 0` into the **End point** text field.
11. Type `100` into the **Samples** text field.
12. Click the **Query** button. VisIt will create a lineout using the specified point and add a curve to vis window 2. Lineouts for 3D variables can be performed through the **Query** window!
13. Delete vis window 2.
14. Delete all of the plots from vis window 1.

## Exercise 8e) Plot MinMax Query (optional)

In this exercise, we use the MinMax query for a plot to determine the minimum and maximum values for a plot of a nodal variable. We want to find a zone that contains the node where the highest value occurs and plot only that one zone.

1. Open *noise.silo* on your local computer.
2. Make a Pseudocolor plot of *hardyglobal* and click the **Draw** button.
3. Open the **Queries** window by selecting **Queries ...** from the **Main** window's **Controls** menu.
4. Select the **MinMax** query from the **Queries list**.
5. Click the **Query** button to make VisIt calculate the minimum and maximum values in the plot.

6. Open the **Threshold operator attributes** window and type the maximum value reported by the query into the **Lower bound** text field.
7. Click the **Apply** button and answer **Yes** when VisIt asks if you want to apply the Threshold operator.

### Exercise group 9: Making it pretty

VisIt provides a lot of flexibility for changing the look and feel of plots so they can be beautified for presentations. Often, changing the color table, lighting, or adding annotations can improve the look of a plot and make it more appealing.



#### Exercise 9a) Color tables

1. Open *multi\_curve2d.silo* on your local computer.
2. Create a Pseudocolor plot of *d* and click the **Draw** button.
3. Open the **Pseudocolor plot attributes** window.
4. Make the Pseudocolor plot use the **Default** color table, so it will use whichever color table is the active continuous color table. Click the **Apply** button and dismiss the window.
5. Open the **Color table** window by clicking on the **Color table ...** option in the **Main** window's **Controls** menu.
6. Change the active continuous color table to *calewhite* by selecting *calewhite* from the list of **Continous color tables** near the top of the **Color table** window. Click the **Apply** button for the change to take effect. Notice how the Pseudocolor plot now uses the new active continuous color table.
7. Change the active continuous color table a few more times.
8. Type *democolortable* into the **Name** text field and then click the **New** button to create a new color table called *democolortable* that is based on the color table that is highlighted in the color table list in the **Manager** area.
9. Change the number of color control points by typing a new number into the **Number of colors** text field and pressing Enter to cause the color table to get a new number of **color control points**.
10. Move the **color control points** around by clicking on them and dragging them to a new location.
11. Change the colors for the **color control points** by right-clicking on them and selecting a new color from the **color palette**. You can also use the **Red**, **Green**, **Blue** color sliders to set the color directly for the **active color control point**.
12. To make a **color control point** active, click on it with the mouse.
13. Click on the **Align** button if you want to evenly distribute the **color control points**.
14. Change the active continuous color table to be *democolortable* by selecting *democolortable* from the list of **Continuous color tables**.
15. Click the **Apply** button. The Pseudocolor plot in the vis window should now be using your new color table.

## Exercise 9b) 2D Annotation settings

This exercise will familiarize you with the basics of setting 2D annotation options using the controls on the **2D** tab in the **Annotation** window. The controls on the **3D** tab set the annotation options for the 3D axes but since the procedure for setting their attributes is similar to setting the attributes for the 2D axes, we will not have an exercise to set the attributes for 3D axes.

1. Use the plot that was set up in the previous exercise.
2. Open the **Annotation** window by clicking the **Annotation ...** option in the **Main** window's **Controls** menu.
3. Click on the **2D** tab to see the controls for setting 2D annotations, which mainly allow you to set the attributes for the 2D plot axes.
4. Turn off the axes by clicking **Draw axes** and clicking the **Apply** button. Notice that the axes turn off in the vis window. Turn the axes back on.
5. Turn off the axis labels by clicking the **Axis labels** check boxes for both **X** and **Y**. click the **Apply** button. Note that the axis labels disappear but the axis titles are still visible.
6. Turn on grid lines for both X and Y dimensions by clicking the **Grid lines** check boxes for **X** and **Y**. Click the **Apply** button.
7. Choose a thicker line width to use for drawing the axes by picking a new line width from the **Line width** combo box. Click the **Apply** button.




## Exercise 9c) Setting window colors

The **Colors** tab in the **Annotation** window allows you to set the background and foreground colors for the active vis window. Color selection is very crucial in the creation of a presentation quality image. The default window colors, while good for

everyday use, are not very good for presentations because they are flat and do not help to convey depth. VisIt provides more interesting gradient color backgrounds that instantly improve the quality of an image that will be used in presentations.

1. Delete the plot from the previous exercise.
2. Open *wave.visit* on your local computer.
3. Create a Pseudocolor plot of *pressure* and click the **Draw** button.
4. Click the **Gradient** radio button so you can change the gradient background settings. Click the **Apply** button. This should change the background to a radial blue and black gradient.
5. Change the **Foreground** color to white and click the **Apply** button.
6. Experiment with different gradient styles by choosing a new gradient style from the **Gradient style** combo box and clicking the **Apply** button. At the same time, experiment with new gradient colors.




### Exercise 9d) Annotation objects

VisIt provides two simple annotation objects that can be used to improve the quality of an image destined for a presentation. The first annotation object is a time slider that is useful for showing the progress through time in an animation. The second annotation object is a 2D text object that can be placed anywhere in the vis window and can display arbitrary text. The 2D text annotation is especially useful for adding classification banners to an image.

1. Use the plot from the previous exercise
2. Click on the **Objects** tab in the **Annotation** window.



3. Click on the **Time slider** button to create a new time slider object. Click the **Apply** button and look for the time slider in the lower left corner of the annotation window.
4. Increase the height of the time slider to 7% by incrementing the value in the **Height** spin box a few times. Click the **Apply** button.
5. Select a new start color by clicking on the **Start color** button and choosing a new color from the color palette. Click the **Apply** button.
6. Click the **Text** button to create a new 2D text annotation object. Note that the window changes so the attributes for the 2D text annotation show instead of the attributes for the time slider.
7. Type *Unclassified* into the **Text** text field.
8. Click the **Bold** check box to make the text be bold.
9. Click the **Shadow** check box to make the text have a slight shadow under it.
10. Click the **Apply** button.
11. Type *0.36 0.95* into the **Lower** left text field and click the **Apply** button to move the annotation to the upper middle of the vis window.
12. Change the width to be *30%* using the **Width** spin button and click the **Apply** button.
13. Use the **Animation slider** to change the time so you can see the time slider annotation update a few times.
14. Use the **Animation slider** to get back to the first time state.
15. Delete the plot.




### Exercise 9e) Lights (optional)

Lights can make a lot of difference in the brightness of a plot that uses lighting like the Pseudocolor plot. If a plot is too dark, changing the light or adding another light can vastly improve the plot's appearance. This exercise is not so concerned with making a plot look better as it is with showing you how to use the lighting controls so we will use multiple colored lights.

1. Open *globe.silo* on your local computer.
2. Create a Pseudocolor plot of *w*.
3. Open the **Pseudocolor plot attributes** window and make the Pseudocolor plot use the *xray* color table.
4. Click the **Apply** button.
5. Open the **Annotation** window, click the **Colors** tab, and click the **Solid** radio button so the vis window will use a solid background color. Change the background color to black and click the **Apply** button. Dismiss the **Annotation** window. The vis window should now have a big white globe on a black background.
6. Reset the view using the **Reset view** toolbar button in the vis window.
7. Turn on auto update mode in the **Main** window by clicking the **Auto update** check box above the plot list. This will eliminate the need to keep clicking the **Apply** button and will work better for designing lights, which is largely a trial and error exercise.
8. Open the **Lighting** window by clicking on the **Lighting ...** option in the **Main** window's **Controls** menu.
9. The **Lighting** window will have on its left side an image (the test sphere) that looks similar to the plots that we've set up. In fact, we set the plots up to look like the test sphere in the lighting window so you can see more easily how lighting affects a plot. Nestled in with the test sphere, there is a small blue arrow that you can drag around to change the lighting. Drag the small blue arrow and release it and watch lighting on the test sphere change. Since **Auto update** mode is on, the vis window will also update.
10. Move the blue arrow a few times to see what happens.
11. Type *0 0 -1* into the **Direction** text field and press Enter. This will reset the light so it shines into the scene. Change the color to red.
12. Select light 2 by clicking on 2 in the Active light combo box.
13. Type *0 -1 0* into the **Direction** text field and press the Enter key.
14. Change the light's color to green.
15. Turn the light on by clicking the **Enabled** check box. The vis window should have a mostly red sphere with a soft green highlight coming down from above.
16. Select light 3 by clicking on 3 in the **Active light** combo box.
17. Type *-1 0 0* into the **Direction** text field and press the Enter key.
18. Change the light's color to blue.
19. Turn the light on by clicking the **Enabled** check box. The vis window should have a mostly red sphere with a soft green highlight coming down from above and a soft blue highlight coming from the right.
20. Rotate the plot in the vis window. Notice how the highlights never seem to change because the lights are fixed in space because they are camera lights.

21. Change the blue light to be an object light by selecting *Object* from the **Light type** combo box.
22. Make light 2 (the green light) be the active light by selecting 2 from the **Active light** combo box.
23. Change the light type to *Object*.
24. Make light 2 (the red light) be the active light by selecting 1 from the **Active light** combo box.
25. Change the light type to *Object*.
26. Click on the **Preview** radio button in the **Lighting** window to show all lights and drag the mouse over the test sphere to rotate the test sphere. Note that the lights are now fixed to the object.
27. Rotate the plot in the vis window. The behavior will be the same as for the **Lighting** window's test sphere
28. Click the **Reset** button in the **Lighting** window to restore the default light attributes, which are the light attributes that were last saved. Since we never clicked the **Make default** button for lights, this will restore VisIt's lighting to use a single white camera light.
29. Turn off **Auto update** in the **Main** window.
30. Delete the plot.



## Exercise Group 10: Animation and Keyframing

### Exercise 10a) Session files

VisIt session files save all of the information necessary for VisIt to create the same plots later.

1. Open *wave.visit* on your local computer.
2. Create a Pseudocolor plot of *pressure*.
3. Create a Mesh plot of *quadmesh*.
4. Click the **Draw** button.
5. Open the **Annotation** window and make the vis window have a gradient background and change the vis window foreground color to white.
6. Save a session file by choosing **Save session ...** from the **Main** window's **File** menu. You will be prompted for the name of the session file so save the session file as *wave.vses*.
7. Quit VisIt.
8. Start VisIt again.
9. Click **Restore session ...** from the **Main** window's **File** menu. Locate and select the *wave.vses* session file that you previously saved. Once you select the session file, VisIt will read in the session file and restore everything to where you were when you saved the session file.

### Exercise 10b) Movie generation using session files

VisIt provides a utility for generating movies called `visit -movie`. If you open up a command line shell, you can execute `visit -movie` with the name of a session file and VisIt will create a movie of the plots described by the session file. In Windows, VisIt session files can be used to automatically generate movies. If you right click on a session file, there are options to generate movies at different resolutions. If you choose to generate a movie like this, Windows runs `visit -movie` with the session file that you clicked on.

1. Open a **Command prompt** window by choosing **Command prompt** window from the **Accessories** menu in the **Programs** menu in the **Windows Start** menu.
2. Type `cd C:\Program files\LLNL\VisIt 1.4.1\` to change the active directory to the directory where VisIt was installed.
3. Type `visit -movie -sessionfile wave.vses -geometry 1000x1000 -format tiff` to generate 1000 pixel \* 1000 pixel TIFF format movie frames of the plots described by the *wave.vses* session file.
4. Open **My Computer** on the Windows desktop or in the **Windows Start** menu. Navigate to `C:\Program files\LLNL\VisIt 1.4.1\` where VisIt was installed. This is where VisIt session files are saved by default.
5. Right click on *wave.vses* and choose the **Generate 480x480 movie** option. This will cause VisIt to generate TIFF files for the visualization described by the *wave.vses* session file.

### Exercise 10c) Keyframing

VisIt allows you to set plot, view, and database keyframes for your animation. This exercise will familiarize you with setting plot attribute and view keyframes.

1. Open the **Animation** window by clicking **Animation ...** in the **Main** window's **Controls** menu.
2. Click the **Cache animation for faster playback** check box so VisIt caches the animation while generating it so when the animation starts playing again from the beginning, it plays faster because it does not have to be regenerated by the compute engine.
3. Open *wave.visit* on your local computer.
4. Create a Pseudocolor plot of *pressure*.
5. Create a Mesh plot of *quadmesh*.
6. Click the **Draw** button.
7. Open the **Keyframe** window by clicking on the **Keyframing ...** option in the **Main** window's **Controls** menu.
8. Turn on Keyframing by clicking the **Keyframing enabled** check box. Click the **Apply** button in the **Keyframe** window.
9. Select the Mesh plot in the **Plot list** and double click it to open the **Mesh plot attributes window**.
10. Make the mesh plot use yellow lines. Turn off the **Use foreground** check box and change the **Mesh color** to yellow. Click the **Apply** button.
11. Rotate the view a little in the vis window.
12. Open the **View** window by clicking on **View ...** in the **Main** window's **Controls** menu. Click on the **Advanced** tab. Click on the **Copy view from camera** check box to make sure that it is turned on. Click the **Apply** button.
13. Click the **Make camera keyframe from view** button to set a view keyframe.
14. Since we're keyframing a database with multiple time states, VisIt will have more than one possible time slider: a time slider for *wave.visit* and a time slider for the keyframing frame. The active time slider should be the keyframing time slider. Drag the **Animation slider** to frame 37.
15. Double click on the Pseudocolor plot's plot entry in the **plot list**. This will select the Pseudocolor plot and also open the **Pseudocolor plot attributes** window. Change the plot's opacity to 10% and click the **Apply** button. This will set a plot attributes keyframe for the Pseudocolor plot at the current animation frame.
16. Rotate the plot a little in the vis window and zoom in a little too.
17. Click the **Make camera keyframe from view** button in the **View** window to set a view keyframe at the current animation frame.
18. Drag the **Animation slider** to frame 70.
19. Double click the Mesh plot's plot entry in the **plot list**. When the **Mesh plot attributes** window opens, change its Mesh color to be red. Make the plot use a heavier line width too and click the **Apply** button to set a plot attributes keyframe for the Mesh plot.
20. Double click the Pseudocolor plot's plot entry in the **plot list**. When the **Pseudocolor plot attributes** window opens, set the plot's opacity to 100% and click the **Apply** button.
21. Rotate the plot a little in the vis window.
22. Click the **Make camera keyframe from view** button in the **View** window to set a view keyframe.

23. Save a session file called *keyframe.vses* so you could restart VisIt later and get back all of the setup that you've just done.
24. Click the **Play** button and watch the animation generate and play.
25. Once you've watched the animation enough, click the **Stop** button and drag the **Animation slider** back to frame 0. Delete all of the plots.

### Exercise 10d) Running the CLI (optional)

VisIt's Python command line interface (CLI) is a Python interpreter that imports the VisIt Python module when it starts up. This allows what is an ordinary Python interpreter to control VisIt via scripting by calling functions that give VisIt instructions to open databases, create plots, etc.

1. VisIt's Python command line interface (CLI) is available in the VisIt program group in the Windows start menu. To run VisIt's CLI, click on VisIt Command Line Interface in the VisIt program group.
2. To open a database using the CLI, you must use the *OpenDatabase* function from the VisIt module. The *OpenDatabase* function takes the name of a database to open. The name of the database to open can be a relative path to a file on disk or it can be a host qualified file name to open a file on a remote computer. Since the start up path on for the CLI on Windows is the VisIt installation directory, we can open up VisIt's *noise.silo* database by typing *OpenDatabase("data\\noise.silo")* at the Python command prompt and pressing the Enter key.
3. The Python function to call if you want to add a plot from the open database is *AddPlot*. The *AddPlot* function takes two arguments. The first argument is a string containing the name of the plot type to create (e.g. "Pseudocolor", "Mesh"). The second argument is a string containing the name of the variable to plot. To add a Pseudocolor plot of the *hardyglobal* variable, type *AddPlot("Pseudocolor", "hardyglobal")* at the Python prompt and press the Enter key.
4. You can list the plots that have been created by calling *ListPlots()*. Type *ListPlots()* at the Python prompt and press the Enter key.
5. The Python function to call if you want to add an operator is *AddOperator*. The *AddOperator* function takes a string argument that is the name of the operator that you want to apply. To apply a Slice operator, type *AddOperator("Slice")* at the Python prompt and press the Enter key.
6. If you have the default Slice operator attributes in your configuration settings, adding a Slice operator sliced the Pseudocolor plot and projected it to 2D. Let's set the Slice operator attributes so the slice is left in 3D. Each operator or plot has a Python object type that contains the attributes for that operator or plot. You can create an object to set the slice operator attributes calling the *SliceAttributes* function. The name of the function to call in the general case is the name of the function plus the word "Attributes". The name of the function that you would call for a Pseudocolor plot is *PseudocolorAttributes*. Type *s = SliceAttributes()* at the Python prompt and press the Enter key.
7. The object *s* now contains slice operator attributes. Print the contents of *s* by typing *print s* at the Python prompt and pressing the Enter key.

8. Let's make the slice be left in 3D now. Type `s.project2d = 0` at the Python prompt and press the Enter key. This only sets the attributes for `s`. Next we have to tell VisIt to use `s` as the new slice operator attributes.
9. Type `SetOperatorOptions(s)` at the Python prompt and press the Enter key. The `SetOperatorOptions` function takes an operator attributes object. In this case, we're passing a slice operator attributes object and VisIt will apply it to the selected plots in the plot list.
10. Now for a small demonstration of why scripting is so powerful. Type the following code at the Python prompt: *(Note that the `>>>` and `...` are the Python prompts and are only shown for proper indentation. Do not type those characters)*

```
>>> s.originType = s.Percent
>>> for i in range(0,100,5):
...     s.originPercent = i
...     SetOperatorOptions(s)
```

11. The above code should make a slice plane move through the data in 3D.
12. To make the slice plane move through each dimension, type the following code at the Python prompt:

```
>>> normals = ((1,0,0), (0,1,0), (0,0,1))
>>> for n in normals:
...     s.normal = n
...     for i in range(0,100,2):
...         s.originPercent = i
...         SetOperatorOptions(s)
```

13. Type Ctrl+Z and press the Enter key at the Python prompt to exit the CLI.

### Exercise 10e) Using the CLI to generate a movie (optional)

VisIt's CLI can be run with a `-nowin` flag to make it run without a window and you can give a `-s` argument with the name of a script to make the CLI execute a script.

1. Open a Command prompt window by clicking **Command prompt** in the **Accessories** menu in the **Windows Start** menu.
2. Type `notepad.exe` at the command prompt to launch the Notepad application so you can type in a new VisIt Python script.

```
OpenDatabase("localhost:C:\\Program Files\\LLNL\\VisIt
1.4.1\\data\\noise.silo")
AddPlot("Pseudocolor", "hardyglobal")
AddOperator("Slice")
s = SliceAttributes()
s.project2d = 0
```

```
s.originType = s.Percent
SetOperatorOptions(s)
DrawPlots()
normals = ((1,0,0), (0,1,0), (0,0,1))
for n in normals:
    s.normal = n
    for i in range(0,100,2):
        s.originPercent = i
        SetOperatorOptions(s)
        SaveWindow()
```

3. Save the script to a file called *movie.py*.
4. Type “*C:\Program Files\LLNL\VisIt 1.4.1\visit.exe*” *-cli -nowin -s movie.py* at the command prompt to make VisIt’s CLI generate the movie frames with no window.